

The Resource for Virology Research

# HA(H3N2)(A/Perth/16/2009) Hemagglutinin ELISA Development Kit Catalog Number: IT-E3Ag-H3N2-Perth/16/2009

**Description:** HA(H3N2)(A/Perth/16/2009) Hemagglutinin ELISA Development Kit contains the key components required for the quantitative analysis of HA(H3N2)(A/Perth/16/2009) Hemagglutinin (HA) concentrations in cell culture supernatants and serum within the range of 0.5-32 ng/ml in a sandwich ELISA format. The components supplied in this kit are sufficient to assay HA(H3N2)(A/Perth/16/2009) in five 96-well ELISA plates.

#### REAGENTS PROVIDED

**Capture Antibody:** 100µ1 of 1mg/ml anti-HA(H3N2)(A/Perth/16/2009) monoclonal antibody. HA(H3N2)(A/Perth/16/2009) Standard: 50µ1 of 50ug/ml recombinant HA(H3N2)(A/Perth/16/2009).

Detection Antibody: 50µl of biotinylated monoclonal antibody against HA(H3N2)(A/Perth/16/2009).

Streptavidin-HRP Conjugate: 50µl of HRP-conjugated streptavidin.

## RECOMMENDED MATERIALS & SOLUTIONS\*

ELISA 96-well plates (Corning Prod # 3590 or

equivalents)

**Block Buffer:** 5% milk in PBS

Wash Buffer: 0.05% Tween-20 in PBS Diluent: 0.05% Tween-20, 0.5% milk in PBS **Substrate:** TMB Peroxidase Substrate Stop Solution: 2N Sulfuric Acid

\*Alternatively, these could be purchased under Cat.# IT-200-002


- ELISA Plate/Buffer/Substrate Kit.

#### PLATE PREPARATION

- 1. For each 96-well plate, dilute 20µl of Capture Antibody with 10.5ml of 1xPBS to prepare a coating solution. Immediately add 100µl of the coating solution to each well. Seal the plate and incubate overnight at 4°C.
- 2. Remove the coating solution by aspirating or decanting. Invert the plate and blot it briefly against clean paper towels.
- Add 300µl of Block Buffer to each well. Incubate for at least 1 hour at room temperature.
- Aspirate to remove Block Buffer and wash the plate 4 times with 300µl of Wash Buffer per well.

### ASSAY PROCEDURE

- 1. Standard/Sample: Dilute the standard with Diluent to eight concentrations (32ng/ml, 16ng/ml, 8ng/ml, 2ng/ml, 1 ng/ml, 0.5 ng/ml, 0 ng/ml). 4ng/ml, Immediately add 100µl of Standard and sample to each well in triplicate. Incubate at room temperature for at least 1 hour.
- **2. Detection:** Aspirate and wash plate 4 times. Dilute 10µl of Detection Antibody with 10.5ml of Diluent to prepare a detection solution. Add 100µl of the detection solution into each well. Incubate at room temperature for at least 1 hour.
- 3. Streptavidin Peroxidase: Aspirate and wash plate 4 times. Dilute 10µl of Streptavidin-HRP Conjugate with 10.5ml of Diluent. Add 100µl into each well. Incubate at room temperature for 30 minutes.
- Substrate/Stop: Aspirate and wash plate 4 times. Add 100µl of TMB Peroxidase Substrate into each well. Incubate at room temperature for 20 minutes. Then add 100µl of Stop Solution to each well.
- 5. Read: Determine the optical density of each well within 30 minutes using a microplate reader set to 450nm.
- 6. Analysis: Average the triplicate reading for each standard, control, and sample, then subtract the average zero standard optical density. Create a standard curve by reducing the data using computer software capable of generating a four parameter logistic (4-PL) or other curve-fit. The HA(H3N2)(A/Perth/16/2009) concentration sample can be determined by regression analysis. If samples have been diluted, the concentration calculated from the standard curve must be multiplied by the dilution factor.



#### Reference

1. John R. Crowther. The ELISA Guidebook (Methods in Molecular Biology), Humana Press, 2000.